ExLibris Aleph

Z16 – SUBSCRIPTION INFORMATION

The Z16 record contains copy-specific information for serials control and it is used by the system to create expected issues (item records).


Note that if there is a link between the subscription and the holdings record, the location information in the subscription record is overridden using the location information from the holdings record (from the 852 location field of the holdings record). The exact subfields from the 852 field that update location information are defined in the "correct_852_subfields" environment variable in the alephe/aleph_start file.

In the following table, (X) denotes an alphanumeric field and (9) denotes a numeric field. All alphanumeric fields are left-aligned with trailing spaces; all numeric fields are right-aligned with leading zeros. Decimal positions are indicated by the symbol V. The total number of decimal digits is designated by the number of nines following the V.


02 Z16-REC-KEY.		
03 Z16-DOC-NUMBER	PICTURE	9(9).
03 Z16-COPY-SEQUENCE	PICTURE	9(5).
03 Z16-SEQUENCE	PICTURE	9(3).
02 Z16-COPY-DATA.		
03 Z16-ALPHA	PICTURE	
03 Z16-SUB-LIBRARY	PICTURE	X(5).
03 Z16-COPY-FROM-DATE	PICTURE	9(8).
03 Z16-COPY-TO-DATE	PICTURE	9(8).
03 Z16-VENDOR-CODE	PICTURE	X(20).
03 Z16-VENDOR-ORDER-NUMBER	PICTURE	X(30).
03 Z16-ORDER-NUMBER	PICTURE	X(30).
03 Z16-DELIVERY-TYPE	PICTURE	X(2).
03 Z16-DELAY	PICTURE	9(3).
03 Z16-ID	PICTURE	X(12).
03 Z16-DIRECT-DELIVERY	PICTURE	X(1).
03 Z16-ITEM-STATUS	PICTURE	X(2).
03 Z16-COLLECTION	PICTURE	X(5).
03 Z16-LOCATION-TYPE	PICTURE	X(1).
03 Z16-LOCATION	PICTURE	X(80).
03 Z16-LOCATION-2-TYPE	PICTURE	X(1).
03 Z16-LOCATION-2	PICTURE	X(80).
03 Z16-LABEL	PICTURE	X(1).
03 Z16-DISCARD-BIND	PICTURE	X(2).
03 Z16-CLAIM	PICTURE	X(1).
03 Z16-CLAIM-2	PICTURE	9(3).

© Ex Libris Ltd., 2009 Z16 Version 20.0 April 30, 2009


03 Z16-CLAIM-3 03 Z16-CLAIM-4 03 Z16-NOTE	PICTURE 9(3). PICTURE 9(3). PICTURE X(100).
03 Z16-CHECK-IN-NOTE	PICTURE X(300).
03 Z16-ITEM-STATISTIC 02 Z16-HOL-DOC-NUMBER-X.	PICTURE X(10).
03 Z16-HOL-DOC-NUMBER-X.	PICTURE 9(9).
02 Z16-TEMP-LOCATION	PICTURE X(1).
02 Z16-COPY-ID	PICTURE X(5).
02 Z16-DEPOSITORY-ID	PICTURE X(5)



Z16-REC-KEY			
Z16-DOC-NUMBER	M	9(9)	DESC: ADM system number. CONV: System number of the administrative record associated to the subscription.
Z16-COPY-SEQUENCE	М	9(5) Leading zeroes	DESC: Sequence number of subscription within an ADM record. CONV: Sequential number, beginning with 00001.
Z16-SEQUENCE	М	9(3)	DESC: Additional sequence. Used when subscription details are changed commencing from a certain date (e.g. assigned to a different sublibrary or vendor). Z16-COPY-SEQUENCE remains the same and Z16-SEQUENCE is used to identify the changed record. CONV: Enter 001 as default.
Z16-COPY-DATA			
Z16-ALPHA	M	X(1)	DESC: ALPHA code of the record. Use L for all scripts (e.g. Latin, Greek, Cyrillic, etc.). CONV: L.
Z16-SUB-LIBRARY	М	X(5) Upper case	DESC: Sublibrary to which the subscription belongs. If the Z16 record is linked to an HOL record through the Z16-HOL-DOC-NUMBER field, then the sublibrary is inserted automatically by the system with the contents of subfield \$b from the location field of the HOL record (852 field). CONV: Sublibrary code.
Z16-COPY-FROM-DATE	M	9(8) Format: YYYYMMDD.	DESC: Starting date of subscription. When the subscription is created from the Items/Subscriptions node of the order from the Order tab of the Acquisitions/Serials module, the starting date is defaulted to the value entered in the "Subscription start" field (Z68- SUBSCRIPTION-DATE-FROM) of the order record. CONV: Date equal to or earlier than current year received.
Z16-COPY-TO-DATE	М	9(8) Format: YYYYMMDD	DESC: Ending date of subscription. When the subscription is created from the Items/Subscriptions node of the order from the Order tab of the




			 Acquisitions/Serials module, the ending date is defaulted to the value entered in the "Subscription end" field (Z68-SUBSCRIPTION-DATE-TO) of the order record. CONV: Date equal to or later than current year received; 20991231 for open-ended subscription.
Z16-VENDOR-CODE	M	X(20) upper case	DESC: Vendor's code. CONV: Code must match the vendor's code in the vendor's record (Z70-VENDOR-CODE).
Z16-VENDOR-ORDER- NUMBER	0	X(30)	DESC: Information by which the vendor identifies the subscription CONV: Blank or relevant number.
Z16-ORDER-NUMBER	0	X(30)	 DESC: Order number; if equal to order number of the Acquisition order, can be used for combined reports. CONV: Acquisition order field is Z68-ORDER-NUMBER.
Z16-DELIVERY-TYPE	M	X(2)	 DESC: The way in which the supplier dispatches the material. For example: A= Airmail S= Surface C= Courier AF = Airfreight CONV: Any alphanumeric character. Should be coordinated with values in the pc_tab_exp_field.eng table of the library's tab directory.
Z16-DELAY	М	9(3)	 DESC: Number of days that elapse between publication date and expected arrival. Used for calculating estimated date of arrival for each issue. CONV: Relevant or default number of days.
Z16-ID	O/ M	X(12)	 DESC: ID of the user for whom the subscription is intended. CONV: Matches the Z303_ID field. Mandatory if Z16-DIRECT-DELIVERY is Y; otherwise optional.
Z16-DIRECT-DELIVERY	М	X(1)	 DESC: Indicates if issues should by-pass library check-in and be delivered directly to user (see Z16_ID). Values are: Y = Yes




_


			N = No
			CONV: "N" if Z16-ID is blank.
Z16-ITEM-STATUS	M	X(2)	 DESC: Loan status, copied to item's Z30-ITEM-STATUS. Values are 01-98. CONV: Relevant value. Values must be defined in the tab15 (Item statuses) table
Z16-COLLECTION	0	X(5) Upper case	of the library's tab directory. DESC: Code identifying the collection (copied to item's Z30-COLLECTION).If the Z16 record is linked to an HOL record through the Z16-HOL-DOC- NUMBER field, then the collection is
Z16-LOCATION-TYPE	0	X(1)	 DESC: The location type is the method the library will use to arrange the item on the shelf. This field is copied to the item's Z30-LOCATION-TYPE field when items are created for the expected issues. It defines the type of location assigned in the Z16-LOCATION / Z30-LOCATION field. If the Z16 record is linked to an HOL record through the Z16-HOL-DOC-NUMBER field, then the location type is inserted automatically by the system with the contents of the first indicator of the location field from the HOL record (852 field).
			 The values are defined in the \$data_tab/ pc_tab_exp_field.eng. MARC 21 values supported by ALEPH are: 0 - Library of Congress classification 1 - Dewey Decimal classification 2 - National Library of medicine classification. 3 - Superintendent of Documents classification. 4 - Shelving control number



	1		
			5 - Shelving Form of Title
			6 - Shelved separately
			7 - Source specified in \$\$2
			8 - Local classification
			CONV: Blank or a relevant value.
Z16-LOCATION	0	X(80)	DESC: An alphanumeric code that
			identifies the shelf location of the item. If
			the Z16 record is linked to an HOL
			record through the Z16-HOL-DOC-
			NUMBER field, then the location is
			inserted automatically by the system with
			the contents of subfield \$h/\$i/\$j/\$l/\$k/\$m
			from the location field of the HOL record
			(852 field).
	0	37/1)	CONV: Blank or relevant string.
Z16-LOCATION-2-TYPE	0	X(1)	DESC: As Z16-LOCATION-TYPE.
Z16-LOCATION-2	0	X(80)	DESC: Additional shelving location of
			the item.
			CONV: Blank or relevant string.
Z16-LABEL	Μ	X(1)	DESC: Defines if a label should be
			printed automatically when the arrival of
			an issue is registered.
			Values are:
			$\mathbf{Y} = \mathbf{Y}\mathbf{e}\mathbf{s}$
			N = No
			CONV: Relevant value.
Z16-DISCARD-BIND	_	X(2)	DESC: Not in use.
		(-)	CONV: Leave blank.
Z16-CLAIM	М	X(1)	DESC: This field determines whether
		11(1)	claims for late issues of the subscription
			will be included in the batch output of
			-
			claims to vendor. Values are: $\mathbf{Y} = \mathbf{Y}$ es
			$\mathbf{N} = \mathbf{N}\mathbf{o}$
			$\mathbf{I} = $ Irregular
			If you select the Y option, then claims for
			late items of this subscription of the serial
			are included in the batch of claims that
			are printed using the Print Claims
			service. If you select No or Irregular,
			claims are not automatically sent.
			However, the items will appear in the
			claim report (serial-04).
			CONV: Relevant value.
Z16-CLAIM-2	М	9(3)	DESC: Number of days that elapse
		Leading zeroes	between first claim and second claim
		Leading Zeroes	CONV: 000 to 999.
			CONV: 000 10 999.



Z16-CLAIM-3	М	9(3)	DESC: Number of days that elapse
		Leading zeroes	between second claim and third claim CONV: 000 to 999
Z16-CLAIM-4	Μ	9(3)	DESC: Number of days that elapse
		Leading zeroes	between third claim and following claims CONV: 000 to 999.
Z16-NOTE	0	X(100)	DESC: Free text note
		Free text	CONV: Blank or relevant string.
Z16-CHECK-IN-NOTE	0	X(300)	DESC: This note will be displayed when the item is checked in.
		Free text	CONV: Blank or relevant text.
Z16-ITEM-STATISTIC	0	X(10)	DESC: Free text field, copied to the
	U	Free text	item's Z30-ITEM-STATISTIC field.
			CONV: Blank or relevant information.
Z16-HOL-DOC-NUMBER-			
X			
Z16-HOL-DOC-NUMBER	Μ	9(9)	DESC: System number of the holdings
		Leading zeroes	record to which the subscription is
			associated.
			CONV: System number of the
		T T(4)	associated holdings record or zeroes.
Z16-TEMP-LOCATION	Μ	X(1)	DESC: This is a toggle field that
			indicates to the system that the location
			information (sublibrary, collection, call number, and call number type) for the
			subscription record should not be updated
			from the holdings record. This
			information is copied to item's Z30-
			TEMP-LOCATION field when items are
			created for the expected issues. Values
			are Y and N.
			COVN: Relevant value.
Z16-COPY-ID	0	X(5)	DESC: Copy number or copy identifier.
			If the UPDATE-Z30-COPY flag in the
			tab100 table of the library's tab directory
			is set to 'N', this information is copied to
			the Z30-COPY-ID field of the items
			created for the expected issues. If the flag is set to 'Y', the Z30-COPY-ID is created
			with the contents of the Z16-COPY-
			SEQUENCE field.
			CONV: Blank or relevant value.
Z16-DEPOSITORY-ID	0	X(5)	DESC: Contains the code of the remote
			storage facility assigned to the issues
			belonging to this subscription. This field
			is copied to the item's Z30-
			DEPOSITORY-ID field. The field is



used to indicate that the items "belong" to the remote storage, regardless of the
sublibrary, collection and processing
status fields.
Remote storage codes are defined in the
pc_tab_exp_field.lng table of the
library's tab directory.
CONV: Blank or relevant value.

