

Z700 – ILL Partner

The Z700 is a pw_library Oracle table that contains administrative information about ILL Partners.

An ILL partner is an administrative unit that sends ILL requests to you and/or that responds to your ILL requests for material. Each library or institution that is used as a player (requester or supplier) in the ILL flow, including your own administrative unit, has a partner record in the system.

There are three types of partners: internal partner, shared external partner, and non-shared external partner.

- Internal Partner also known as ILL Unit local administrative unit that handles ILL borrowing and lending activities. An ILL unit can be set up to represent a single sublibrary or a group of sublibraries.
- Shared External Partner a supplier or a requester library which is not a part of any ADM library of your library system; it is external to your library system (for example, another library or a supplier like BLDSC). An external shared partner can be used as a supplier by all ADM libraries.
- Non-shared External Partner a non-shared external partner is the same as a shared external partner, but it can be used as a supplier only by the library which created the partner record.

Each ILL partner (both external and internal) to whom you supply ILL material must have a parallel Patron record.

In the following Z700 table, (X) denotes an alphanumeric field and (9) denotes a numeric field. All alphanumeric fields are left-aligned with trailing spaces; all numeric fields are right-aligned with leading zeros. Decimal positions are indicated by the symbol V. The total number of decimal digits is designated by the number of nines following the V. Note that the decimal point is not stored in the field (for example, if the field definition is 9(4)V99, then 1000 = 10.00).

```
01 Z700.
         02 Z700-REC-KEY.
           03 Z700-INTERNAL-CODE
                                         PICTURE X(20).
         02 Z700-ILL-LIBRARY
                                         PICTURE X(5).
         02 Z700-UNIT
                                         PICTURE X(1).
         02 Z700-PROTOCOL-TYPE
                                         PICTURE X(5).
         02 Z700-REC-KEY-2.
           03 Z700-PROTOCOL-CODE
                                         PICTURE X(50).
         02 Z700-E-INTERFACE.
           03 Z700-SERVER-ADDRESS
                                         PICTURE X(100).
         02 Z700-PRINT.
           03 Z700-PLAIN-HTML
                                         PICTURE X(1).
           03 Z700-LETTER-TYPE
                                         PICTURE 9(2).
           03 Z700-SEND-METHOD
                                         PICTURE X(5).
         02 Z700-NAME-KEY
                                          PICTURE X(40).
```



```
02 Z700-ISO-SUPPLIER-TYPE
                                        PICTURE X(10).
        02 Z700-USER-ID
                                         PICTURE X(50).
        02 Z700-USER-PASSWORD
                                         PICTURE X(50).
        02 Z700-NAME
                                         PICTURE X(150).
02 Z700-GENERAL-ADDRESS.
                                        PICTURE X(100).
          03 Z700-GEN-ADDRESS-1
          03 Z700-GEN-ADDRESS-2
                                         PICTURE X(100).
          03 Z700-GEN-ADDRESS-3
                                         PICTURE X(100).
                                        PICTURE X(100).
          03 Z700-GEN-ADDRESS-4
          03 Z700-GEN-ADDRESS-5
                                         PICTURE X(100).
          03 Z700-GEN-TELEPHONE
                                         PICTURE X(20).
          03 Z700-GEN-FAX
                                         PICTURE X(20).
          03 Z700-GEN-EMAIL-ADDRESS
                                         PICTURE X(60).
          03 Z700-GEN-STRUCTURED-ADDRESS.
            04 Z700-GEN-CITY
                               PICTURE X(50).
            04 Z700-GEN-STATE
                                         PICTURE X(50).
            04 Z700-GEN-ZIP
                                         PICTURE X(20).
            04 Z700-GEN-COUNTRY
                                        PICTURE X(50).
          03 Z700-GEN-CONTACT.
            04 Z700-GEN-CONTACT-1
04 Z700-GEN-CONTACT-2
04 Z700-GEN-CONTACT-3
                                        PICTURE X(200).
                                        PICTURE X(200).
                                        PICTURE X(200).
    02 Z700-SHIPPING-ADDRESS.
                                       PICTURE X(100).
          03 Z700-SHIP-ADDRESS-1
          03 Z700-SHIP-ADDRESS-2
                                        PICTURE X(100).
          03 Z700-SHIP-ADDRESS-3
                                        PICTURE X(100).
          03 Z700-SHIP-ADDRESS-4
                                        PICTURE X(100).
          03 Z700-SHIP-ADDRESS-5
                                        PICTURE X(100).
          03 Z700-SHIP-TELEPHONE
03 Z700-SHIP-FAX
                                        PICTURE X(20).
                                        PICTURE X(20).
          03 Z700-SHIP-EMAIL-ADDRESS PICTURE X(60).
          03 Z700-SHIP-STRUCTURED-ADDRESS.
            04 Z700-SHIP-CITY
                                        PICTURE X(50).
            04 Z700-SHIP-STATE
                                        PICTURE X(50).
            04 Z700-SHIP-ZIP
                                        PICTURE X(20).
            04 Z700-SHIP-COUNTRY
                                        PICTURE X(50).
          03 Z700-SHIP-CONTACT.
            04 Z700-SHIP-CONTACT-1 PICTURE X(200).
04 Z700-SHIP-CONTACT-2 PICTURE X(200).
04 Z700-SHIP-CONTACT-3 PICTURE X(200).
 02 Z700-BILLING-ADDRESS.
          03 Z700-BILL-ADDRESS-1
                                        PICTURE X(100).
          03 Z700-BILL-ADDRESS-2
                                        PICTURE X(100).
          03 Z700-BILL-ADDRESS-3
                                        PICTURE X(100).
          03 Z700-BILL-ADDRESS-4
                                        PICTURE X(100).
          03 Z700-BILL-ADDRESS-5
                                        PICTURE X(100).
          03 Z700-BILL-TELEPHONE
03 Z700-BILL-FAX
                                        PICTURE X(20).
                                         PICTURE X(20).
          03 Z700-BILL-EMAIL-ADDRESS PICTURE X(60).
          03 Z700-BILL-STRUCTURED-ADDRESS.
            04 Z700-BILL-CITY
                                  PICTURE X(50).
            04 Z700-BILL-STATE
                                         PICTURE X(50).
            04 Z700-BILL-ZIP
                                         PICTURE X(20).
                                   PICTURE X(50).
            04 Z700-BILL-COUNTRY
          03 Z700-BILL-CONTACT.
            04 Z700-BILL-CONTACT-1 PICTURE X(200).
```



```
04 Z700-BILL-CONTACT-2
                                PICTURE X(200).
     04 Z700-BILL-CONTACT-3
                                 PICTURE X(200).
02 Z700-NOTE
                               PICTURE X(300).
 02 Z700-COPYRIGHT-STATEMENT
                                 PICTURE X(300).
 02 Z700-OPEN-DATE
                                 PICTURE 9(8).
 02 Z700-UPDATE-DATE
                                 PICTURE 9(8).
 02 Z700-STATUS
                                 PICTURE X(2).
 02 Z700-CON-LNG
                                 PICTURE X(3).
 02 Z700-CATALOGER
                                 PICTURE X(10).
 02 Z700-CURRENCY
                                 PICTURE X(3).
 02 Z700-AVG-SUPPLY-DAYS
                                PICTURE 9(3).
 02Z700-DELIVERY-DELAY
                                PICTURE 9(3).
 02 Z700-LOCATE-TYPE
                                 PICTURE X(10).
 02 Z700-CATALOG-TYPE
                                 PICTURE X(5).
 02 Z700-LOCATE-BASE
                                 PICTURE X(20).
 02 Z700-LOCATE-SERVER
                                 PICTURE X(100).
 02 Z700-LOCATE-CIRC-LIBRARY
                                 PICTURE X(5).
 02 Z700-ADDITIONAL-VENDOR-CODE PICTURE X(30).
02 Z700-BORROWING-ATTR.
   03 Z700-BORROWING-ALLOWED
                                PICTURE X(1).
   03 Z700-AUTO-BORROWING-LOCATE PICTURE X(1).
   03 Z700-CHECK-LOCAL-OWN PICTURE X(1).
   03 Z700-SELF-OWN-L-STATUS
                                PICTURE X(3).
   03 Z700-SELF-OWN-C-STATUS
                                PICTURE X(3).
   03 Z700-REQUEST-PICKUP-LOCS.
     04 Z700-REQUEST-PICKUP-LOC OCCURS 20 PICTURE X(5).
 02 Z700-LENDING-ATTR.
   03 Z700-LENDING-ALLOWED
                                PICTURE X(1).
   03 Z700-AUTO-LENDING-LOCATE PICTURE X(1).
   03 Z700-CIRC-SUB-LIBRARIES.
     04 Z700-CIRC-SUB-LIBRARY OCCURS 20 PICTURE X(5).
   03 Z700-ITEM-LOC-L-STATUS PICTURE X(3).
   03 Z700-ITEM-LOC-C-STATUS
                                PICTURE X(3).
   03 Z700-ITEM-AVAIL-L-STATUS PICTURE X(3).
   03 Z700-ITEM-AVAIL-C-STATUS PICTURE X(3).
```

Z700-REC-KEY			
Z700-INTERNAL-CODE	M	X(20) Upper case	DESC: Unique key by which the system identifies the ILL partner. NOTE: For partners that are used as ILL requesters, set up to 12 alphanumeric characters.
			CONV: Relevant code.

Z700 Version 20

	- ·	T / ->	Description
Z700-ILL-LIBRARY	O/	X(5)	DESC: The ILL library code (XXX40) to
	M		which the ILL partner belongs. Mandatory
			for ILL partner of type ILL Unit (Z700-
			Unit=Y).
			Z700-ILL-LIBRARY field different between
			Shared External Partner and Non-Shared
			External Partner.
			Shared External Partner will have Z700-
			UNIT=N and null in Z700-ILL-LIBRARY.
			Non-Shared External Partner will have
			Z700-UNIT=N and ILL Library code Z700-
			ILL-LIBRARY.
			CONV: Blank or relevant value.
Z700-UNIT	О	X(1)	DESC: Y or N value. This value indicates
2700 01111		11(1)	the type of ILL partner, whether Internal
			· · · · · · · · · · · · · · · · · · ·
			(ILL Unit) or External (shared and non-
			shared).
			Y – The partner is an ILL Unit.
			N – The Partner is not an ILL Unit. It is an
			external partner (shared or non-shared).
			Blank – The same as "N". The Partner is not
			an ILL Unit. It is an external partner (shared
			or non-shared).
			CONV: Relevant value or blank.
Z700-PROTOCOL-TYPE	M	X(5)	DESC: The method in which your library
Z/00-1 KOTOCOL-111L	171	$\Lambda(J)$	- I
			sends communication to the partner.
			Options:
			ISO – ISO TCP protocol
			SLNP – German protocol
			DANZG – Danish Protocol
			LT – Letter: the partner uses letter-based
			communication, e.g.: email, fax, telephone
			BL – ARTel/ARTemail: the partner accepts
			the British Library protocol TX format
			CONV: Relevant code.
Z700-PROTOCOL-CODE	M/	X(50)	DESC: The partner institution symbol. E.g.:
Z/00-1 KOTOCOL-CODE		A(30)	1
	О		EXL:MN_LAW. Mandatory for Z700-
			PROTOCOL-TYPE =ISO. Not relevant for
			all other protocol types.
			CONV: Relevant value or blank.
Z700-E-INTERFACE			DESC: Details for dispatching ILL related
			communication in a non-letter format.
			Relevant only for Z700-PROTOCOL-TYPE
			=ISO.
	L		1001

nber to re sent to Iandatory O. Not s.
Iandatory O. Not
O. Not
S.
_ related
Relevant
E=LT.
is sent to
SEND-
for all
only
only
nail body
ers that are
700-
mended to
alues: 00-
use "00"
rs are sent
mended to
he system
·I.
or the
the
le of the
istance).

Z700-ISO-SUPPLIER-TYPE	О	X(10)	DESC: Not currently in use. For future use:
			define the partner ISO mode for Z700-
			PROTOCOL-TYPE = ISO. Options are
			hard-coded and defined in ILL-ISO-TYPE
			menu of ./ill_library/tab/
			pc_tab_exp_field. <lng>:</lng>
			OCLC - OCLC
			RLG – RLIN
			CONV: Blank.
Z700-USER-ID	O	X(50)	DESC: Not currently in use. For futural
			usage: The library's user ID at the partner.
			CONV: Blank.
Z700-USER-PASSWORD	О	X(50)	DESC: Not in current use. For futural usage:
			The library's user PW at the partner vendor
			list.
			CONV: Blank.
Z700-NAME	M	X(150)	DESC: Name of the partner. It displays in
Z/00 IVIVIE	141	71(130)	the list of partners and is used for sorting the
			vendor list.
			CONV: Relevant text.
7700 CENEDAL ADDRESS			
Z700-GENERAL-ADDRESS			DESC: General address details of the
			partner. If Z700-SHIPPING-ADDRESS and
			Z700-SHIP-STRUCTURED-ADDRESS or
			Z700-BILLING-ADDRESS and Z700-
			BILL-STRUCTURED-ADDRESS sections
			are left empty, the system will use Z700-
			GENERAL-ADDRESS and Z700-GEN-
			STRUCTURED-ADDRESS.
Z700-GEN-ADDRESS-1	О	X(100)	DESC: First line of the partner general
			address. Should be the same as Z700-
			NAME.
			CONV: Relevant text.
Z700-GEN-ADDRESS-2	О	X(100)	DESC: Second line of the partner general
Z/00-OEN-ADDRESS-2		Δ(100)	address.
			CONV: Relevant text.
7700 CEN ADDRESS 2		V(100)	
Z700-GEN-ADDRESS-3	О	X(100)	DESC: Third line of the partner general
			address.
			CONV: Blank or relevant text.
Z700-GEN-ADDRESS-4	O	X(100)	DESC: Fourth line of the partner general
			address.
			CONV: Blank or relevant text.
Z700-GEN-ADDRESS-5	О	X(100)	DESC: Fifth line of the partner general
			address.
			CONV: Blank or relevant text.
Z700-GEN-TELEPHONE	О	X(20)	DESC: The partner general Tel. No.
Z, oo GET, TEEEL HOTTE		11(20)	CONV: Blank or relevant text.
		<u> </u>	COLV. Diank of felevant text.

Z700-GEN-FAX	О	X(20)	DESC: The partner general Fax. No. CONV: Blank or relevant text.
7700 CEN EMAIL		V((0))	
Z700-GEN-EMAIL-	О	X(60)	DESC: The partner general Email address.
ADDRESS			CONV: Blank or relevant text.
Z700-GEN-STRUCTURED-			DESC: Partner's general structured address.
ADDRESS.			
Z700-GEN-CITY	О	X(50)	DESC: The partner general structured
			address: city.
			CONV: Blank or relevant text.
Z700-GEN-STATE	О	X(50)	DESC: The partner general structured
			address: state.
			CONV: Blank or relevant text.
Z700-GEN-ZIP	О	X(20)	DESC: The partner general structured
			address: zip code.
			CONV: Blank or relevant text.
Z700-GEN-COUNTRY	О	X(50)	DESC: The partner general structured
			address: country.
			CONV: Blank or relevant text.
Z700-GEN-CONTACT-1	О	X(200)	DESC: Name of the person to contact at the
			partner for general issues.
			CONV: Blank or relevant text.
Z700-GEN-CONTACT-2	О	X(200)	As Z700-GEN-CONTACT-1
Z700-GEN-CONTACT-3	0	X(200)	As Z700-GEN-CONTACT-1
Z700-SHIPPING-ADDRESS	 	11(200)	DESC: Partner's address for shipping
Z/00 SIMTING /IDDRESS			material. If Z700-SHIPPING-ADDRESS
			and Z700-SHIP-STRUCTURED-ADDRESS
			sections are empty, the system will use
			Z700-GENERAL-ADDRESS and Z700-
			GEN-STRUCTURED-ADDRESS.
Z700-SHIP-ADDRESS-1	О	X(100)	
Z/00-SHIP-ADDRESS-1		A(100)	DESC: First line of the partner shipping address.
7700 CHID ADDDEGG 2		V (100)	CONV: Relevant text.
Z700- SHIP-ADDRESS-2	О	X(100)	DESC: Second line of the partner shipping
			1 1 1
			address.
FF00 GHP ADDEGG 0		T/(100)	CONV: Relevant text.
Z700- SHIP-ADDRESS-3	O	X(100)	CONV: Relevant text. DESC: Third line of the partner shipping
Z700- SHIP-ADDRESS-3	0	X(100)	CONV: Relevant text. DESC: Third line of the partner shipping address.
		, ,	CONV: Relevant text. DESC: Third line of the partner shipping address. CONV: Blank or relevant text.
Z700- SHIP-ADDRESS-3 Z700- SHIP-ADDRESS-4	0	X(100) X(100)	CONV: Relevant text. DESC: Third line of the partner shipping address. CONV: Blank or relevant text. DESC: Fourth line of the partner shipping
		, ,	CONV: Relevant text. DESC: Third line of the partner shipping address. CONV: Blank or relevant text. DESC: Fourth line of the partner shipping address.
Z700- SHIP-ADDRESS-4	0	X(100)	CONV: Relevant text. DESC: Third line of the partner shipping address. CONV: Blank or relevant text. DESC: Fourth line of the partner shipping address. CONV: Blank or relevant text.
		, ,	CONV: Relevant text. DESC: Third line of the partner shipping address. CONV: Blank or relevant text. DESC: Fourth line of the partner shipping address. CONV: Blank or relevant text. DESC: Fifth line of the partner shipping
Z700- SHIP-ADDRESS-4	0	X(100)	CONV: Relevant text. DESC: Third line of the partner shipping address. CONV: Blank or relevant text. DESC: Fourth line of the partner shipping address. CONV: Blank or relevant text.
Z700- SHIP-ADDRESS-4	0	X(100)	CONV: Relevant text. DESC: Third line of the partner shipping address. CONV: Blank or relevant text. DESC: Fourth line of the partner shipping address. CONV: Blank or relevant text. DESC: Fifth line of the partner shipping
Z700- SHIP-ADDRESS-4	0	X(100)	CONV: Relevant text. DESC: Third line of the partner shipping address. CONV: Blank or relevant text. DESC: Fourth line of the partner shipping address. CONV: Blank or relevant text. DESC: Fifth line of the partner shipping address.

Z700-SHIP-FAX	О	X(20)	DESC: The partner shipping Fax. No.
2,00 2111 1111		11(20)	CONV: Blank or relevant text.
Z700-SHIP-EMAIL-	О	X(60)	DESC: The partner shipping e-mail address.
ADDRESS		(= - /	CONV: Blank or relevant text.
Z700-SHIP-STRUCTURED-			DESC: Partner's shipping structured address.
ADDRESS.			rr 8
Z700-SHIP-CITY	0	X(50)	DESC: The partner shipping structured
		, ,	address: city.
			CONV: Blank or relevant text.
Z700-SHIP-STATE	О	X(50)	DESC: The partner shipping structured
			address: state.
			CONV: Blank or relevant text.
Z700-SHIP-ZIP	О	X(20)	DESC: The partner shipping structured
			address: zip code.
			CONV: Blank or relevant text.
Z700-SHIP-COUNTRY	О	X(50)	DESC: The partner shipping structured
			address: country.
			CONV: Blank or relevant text.
Z700-SHIP-CONTACT-1	О	X(200)	DESC: Name of person to contact at the
			partner for shipping issues.
			CONV: Blank or relevant text.
Z700-SHIP-CONTACT-2	0	X(200)	As Z700-SHIP-CONTACT-1
Z700-SHIP-CONTACT-3	0	X(200)	As Z700-SHIP-CONTACT-1
Z700-BILLING-ADDRESS			DESC : Partner's address details for sending
			bills. If Z700-BILLING-ADDRESS and
			Z700-BILL-STRUCTURED-ADDRESS
			sections are empty, the system will use
			Z700-GENERAL-ADDRESS and Z700-
			GEN-STRUCTURED-ADDRESS.
Z700-BILL-ADDRESS-1	О	X(100)	DESC: First line of the partner billing
			address.
			CONV: Relevant text.
Z700-BILL-ADDRESS-2	О	X(100)	DESC: Second line of the partner billing
			address.
			CONV: Relevant text.
Z700- BILL-ADDRESS-3	О	X(100)	DESC: Third line of the partner billing
			address.
			CONV: Blank or relevant text.
Z700- BILL-ADDRESS-4	О	X(100)	DESC: Fourth line of the partner billing
			address.
			CONV: Blank or relevant text.
Z700-BILL-ADDRESS-5	О	X(100)	DESC: Fifth line of the partner billing
			address.
			CONV: Blank or relevant text.
Z700-BILL-TELEPHONE	О	X(20)	DESC: The partner billing Tel. No.
			CONV: Blank or relevant text.

Z700-BILL-FAX	О	X(20)	DESC: The partner billing Fax. No. CONV: Blank or relevant text.
Z700-BILL-EMAIL- ADDRESS	О	X(60)	DESC: The partner billing Email address. CONV: Blank or relevant text.
Z700-BILL-STRUCTURED-ADDRESS.			DESC: Partner's billing structured address.
Z700-BILL-CITY	О	X(50)	DESC: The partner billing structured address: city. CONV: Blank or relevant text.
Z700-BILL-STATE	О	X(50)	DESC: The partner billing structured address: state. CONV: Blank or relevant text.
Z700-BILL-ZIP	О	X(20)	DESC: The partner billing structured address: zip code. CONV: Blank or relevant text.
Z700-BILL-COUNTRY	О	X(50)	DESC: The partner billing structured address: country. CONV: Blank or relevant text.
Z700-BILL-CONTACT-1	О	X(200)	DESC: Name of person to contact at the partner for billing issues. CONV: Blank or relevant text.
Z700-BILL-CONTACT-2	О	X(200)	As Z700-BILL-CONTACT-1
Z700-BILL-CONTACT-3	О	X(200)	As Z700-BILL-CONTACT-1
Z700-NOTE	О	X(300)	DESC: Free text note. CONV: Blank or relevant text.
Z700-COPYRIGHT- STATEMENT	0	X(300)	DESC: Relevant for Australian libraries. The copyright statement text that is sent from the partner with each ISO ILL request that is dispatched to suppliers. Should be set for ILL Unit (Z700-UNIT=Y) of Australian libraries. Works in conjunction with ./alephe/tab100 flag: ILL-MODE=2 (Australian ILL Copyright mode).
Z700-OPEN-DATE	M	9(8) Format: YYYYMM DD	DESC: Date the partner record was opened. CONV: Relevant date or conversion date.
Z700-UPDATE-DATE	M	9(8) Format: YYYYMM DD	DESC: Date the partner record was modified. CONV: Relevant date or conversion date.
Z410-LAST-INTEREST- DATE	M	9(8) Format: YYYYMM DD	DESC: Date the partner record was modified. CONV: Relevant date or conversion date.

Z700-CON-LNG	M	V(2)	DESC: Language of correspondences.
Z/00-CON-LNG	IVI	X(3)	This is the language of the forms that are
			sent to the partner. Possible values are
			defined in LANG menu of ./ill_library/tab/
			pc_tab_exp_field. <lng>.</lng>
5500 615110 655		77(10)	CONV: Valid language code.
Z700-CATALOGER	M	X(10)	DESC: User name of the librarian who last
			updated the partner record.
			CONV: Relevant user name or "CONV".
Z700-CURRENCY	O	X(3)	DESC: The partner local currency.
			CONV: Blank or Z83-CURRENCY-
			NAME.
Z700-AVG-SUPPLY-DAYS	M	9(3)	DESC: Average Supply Days field. Number
		Leading	of days it takes for the partner to supply ILL
		zeroes	material (average supply days).
			Z700- Z700-AVG-SUPPLY-DAYS is used
			as a default value for Z701-AVG-SUPPLY-
			DAYS.
			Z701-AVG-SUPPLY-DAYS is used to
			compute expected date of arrival of the
			material (Z411-EXPECTED-ARRIVAL-
			DATE).
			CONV: Relevant number of days or 000 if
			irrelevant.
Z700-DELIVERY-DELAY	M	9(3)	DESC: Return Delay field. Number of days
Z/00 DEETVERT BEETT	171	Leading	it takes for your library to return ILL
		zeroes	material to the partner. Z700-DELIVERY-
		Zeroes	DELAY is used as a default value for Z701-
			DELIVERY-DELAY. This field is used to
			compute the due date given to the patron for
			an ILL item in the following way: When an
			<u> </u>
			ILL item is received from a supplier for a
			loan, the expected return date is specified by
			the supplier (Z411-EXPECTED-RETURN-
			DATE). The system calculates the due date
			given to the patron as follows: Z411-
			EXPECTED-RETURN-DATE minus Z701-
			DELIVERY-DELAY.
			If you leaveZ700-DELIVERY-DELAY and
			Z701-DELIVERY-DELAY set as zeros,
			ALEPH will use a system-wide default value
			instead. This is set through the
			ill_return_for_user variable in the
			pc_server_defaults
			CONV: Relevant number of days or 000 if
i e	1	1	irrelevant.

	1	T	
Z700-LOCATE-TYPE	M	X(10)	DESC: The mode in which ALEPH will
			attempt to locate material at the partner
			database. Options:
			UNIT- ILL Unit: Indicates that the partner is
			an internal partner. Set this value if Z700-
			UNIT=Y and the ILL unit has all data
			(BIB+Z30 Items) held in an ALEPH format.
			UNITLESS - ILL Unit with no item data in
			ALEPH format: Indicate that the partner is
			an internal partner. Set this value if Z700-
			UNIT=Y and the ILL unit has only BIB data
			in ALEPH format (without Z30-item data of
			ALEPH format.
			ALEPH – ALEPH ILS: Indicates that this is
			an external partner (not part of your ALEPH
			installation) with full ALEPH ILS (BIB+Z30
			Items). This value can be set only if Z700-
			ILL-UNIT=N.
			ITEMLESS - ALEPH ILS with no item
			data in ALEPH format. Indicates that this is
			an external partner (not part of your ALEPH
			installation) with ALEPH ILS with no Item-
			,
			Z30 data in ALEPH format.
			This value can be set only if Z700-ILL-
			UNIT=N.
			EXTERNAL – Z39.50 partner: Indicate that
			this is an external partner that you have set
			Z39.50 gate configuration to access its
			database.
			Set this value if Z700-UNIT=N and the
			partner's base is defined in your Z39.50 gate
			configuration.
			NONE – None of the above options are
			relevant for the partner OR there is no
			information about the partner database OR
			ALEPH is not expected to perform the
			'locate' action at the partner's database. This
			value can be set only for Z700-UNIT=N.
			CONV: Relevant value.

7500 CATALOG 77777	1 3	TT (=)	DEGG EL ALEBYI
Z700-CATALOG-TYPE	M/	X(5)	DESC: The ALEPH catalog type of the
	О		partner.
			Mandatory for Z700-LOCATE-TYPE:
			UNIT, UNITLESS, ALEPH and
			ITEMLESS.
			Not relevant for Z700-LOCATE-TYPE
			NONE and EXTERNAL.
			The options are:
			UV - ALEPH Union View
			SBIB - ALEPH Single Bib database
			CONV: Blank for Z700-LOCATE-TYPE
			=NONE and EXTERNAL. Relevant value
			for all other locate types.
Z700-LOCATE-BASE	M/	X(20)	DESC: The partner base in which the 'BIB
Z, oo Localle Brise	O	11(20)	locate' is performed.
			Mandatory for Z700-LOCATE-TYPE:
			UNIT, UNITLESS, ALEPH, ITEMLESS
			and EXTERNAL.
			Not relevant for Z700-LOCATE-TYPE
			NONE. The base must be one of the bases
			defined in ./alephe_tab/tab_base.eng
			CONV: Blank for Z700-LOCATE-TYPE
			=NONE. Relevant value for all other locate
			types.
Z700-LOCATE-SERVER	M/	X(100)	DESC : The server name and port number of
	О		the partner's Web OPAC; for example:
			goldcoast:8991. Mandatory for Z700-
			LOCATE-TYPE: UNIT, UNITLESS,
			ALEPH, ITEMLESS. Not relevant for Z700-
			LOCATE-TYPE: EXTERNAL and NONE.
			CONV: Relevant value or blank.
Z700-LOCATE-CIRC-	M/	X(5)	DESC: The ADM library code of the
LIBRARY	О		partner. Mandatory for Z700-LOCATE-
			TYPE: UNIT and ALEPH. E.g.: USM50.
			Not relevant for Z700-LOCATE-TYPE:
			UNITLESS, ITEMLESS, EXTERNAL and
			NONE.
			CONV: Relevant value or blank.
Z700-ADDITIONAL-	О	X(30)	DESC: The partner additional code or name
VENDOR-CODE		11(30)	CONV: Relevant text.
Z700-BORROWING-ATTR.			DESC: Internal partner's (ILL Unit)
Z/00-DORROWING-ATTR.			<u>*</u>
			borrowing policy definitions.

Z700-AUTO DODDOWING	M	X(1)	DESC: Indicate whether the internal ILL partner is used as an ILL borrowing center and can serve patron's outgoing requests. Options: Y – ILL Borrowing activity is allowed. N – ILL Borrowing activity is blocked. Internal partners (Z700-UNIT=Y) can have Y or N. External partners (Z700-UNIT=N) must have the value "N". CONV: Relevant value.
Z700-AUTO-BORROWING- LOCATE	M	X(1)	partner's new borrowing requests are automatically handled by the ILL library automatic processing daemon (ue_19). Options: Y – Borrowing request will be handled by ue_19. N – Borrowing request will not be handled by ue_19. Internal partners (Z700-UNIT=Y) can have Y or N. External partners (Z700-UNIT=N) must have the value "N". CONV: Relevant value.
Z700-CHECK-LOCAL-OWN	M	X(1)	partner will first check for self ownership when a new borrowing request is created. Options: 0 – No check 1 – Check for items existence. 2 – Allow ILL if patron is locally blocked. 3 – Block ILL if patron blocked/items available locally. Internal partners (Z700-UNIT=Y) can have one of the above values. External partners (Z700-UNIT=N) must have the value "0". CONV: Relevant value.
Z700-SELF-OWN-L- STATUS	M	X(3)	DESC: Defines the status a "returnable" borrowing request. It is given as a result of local ownership. The only option is LOW (Locally Owned). CONV: Always put: LOW.

7700 CELE OWN C	1.4	V(2)	DESC: Defines the status a "non-returnable"
Z700-SELF-OWN-C-	M	X(3)	
STATUS			borrowing request It is given as a result of
			local ownership. The only option is LOW
			(Locally Owned).
			CONV: Always put: LOW.
Z700-REQUEST-PICKUP-	M/	X(5)	DESC: Defines up to 20 sublibraries from
LOC	О	20	which the in ILL Unit's patrons are allowed
		occurrences	to pick up. Mandatory only for Z700-
			UNIT=Y that its Z700-BORROWING-
			ALLOWED is set to 'Y'.
			The value entered in this field must be
			defined as a valid sublibrary in Col. 1 of
			./alephe/tab/tab_sub_library. <lng>. Only</lng>
			sublibrary of type 1, 2, or 3 can be set in
			Z700-REQUEST-PICKUP-LOCs
			CONV: Blank or relevant value.
Z700-LENDING-ATTR.			DESC: Internal partner's (ILL Unit) lending
			policy definitions.
Z700-LENDING-ALLOWED	M	X(1)	DESC: Indicate whether the internal ILL
			partner is allowed ILL lending.
			Options:
			Y – ILL Lending activity is allowed.
			N – ILL Lending activity is blocked.
			Internal partners (Z700-UNIT=Y) can have
			Y or N.
			External partners (Z700-UNIT=N) must
			have the value "N".
			CONV: Relevant value.
Z700-AUTO-LENDING-	M	X(1)	DESC: Indicate whether all the internal
LOCATE			partner's new lending requests are
			automatically handled by the ILL library
			automatic processing daemon (ue_19).
			Options:
			Y – Lending request will be handled by
			ue 19.
			N – Lending request will not be handled by
			ue_19.
			Internal partners (Z700-UNIT=Y) can have
			Y or N.
			External partners (Z700-UNIT=N) must
			have the value "N".
			CONV: Relevant value.
		j	COTT V. NEIEVAIIL VAIUE.

Z700-CIRC-SUB-LIBRARY	M/	X(5)	DESC: Defines up to 20 sublibraries to
Z/00-CIKC-SUB-LIBRAKT	O	$\frac{\lambda(3)}{20}$	which an item loaned by the ILL Unit must
	O	occurrences	belong. An item can not be loaned by the
		occurrences	ILL Unit if it does not belong to one of these
			sublibraries.
			Mandatory only for Z700-UNIT=Y that its
			Z700-LENDING-ALLOWED is set to 'Y'.
			The value entered in this field must be
			defined as a valid sublibrary in Col. 1 of
			./alephe/tab/tab_sub_library. <lng>. Only</lng>
			sublibrary of type 1 can be set Z700-CIRC-
			SUB-LIBRARY. In case there are more than
			20 sublibraries you may define a group code
			as defined in
			CONV: Blank or relevant value.
Z700-ITEM-LOC-L-STATUS	M	X(3)	DESC: Defines the status to assign to a
			lending request which fails to find a
			matching BIB record when the request is for
			a loan. Options:
			MED – Mediated. The request will go into
			the list of new incoming requests
			for ILL staff to review.
			AUF – Automatic Answer – Unfilled: the
			request goes into the list of
			unfilled incoming requests and a
			message is sent to the requesting
			library that the request is
			unfilled.
			This field is relevant only for internal
			partners.
			Internal partners (Z700-UNIT=Y) can have
			one of the above values.
			External partners (Z700-UNIT=N) must
			have the value "MED".
			CONV: Default MED or relevant value.

Z700-ITEM-LOC-C-STATUS	M	X(3)	DESC: Defines the status to assign to a lending request which fails to find a matching BIB record when the request is for a copy (physical copy or electronic copy). Options: MED – Mediated. The request will go into the list of new incoming requests for ILL staff to review. AUF – Automatic Answer – Unfilled: the request goes into the list of unfilled incoming requests and a message is sent to the requesting library to say that the request is unfilled. This field is relevant only for internal partners.
			Internal partners (Z700-UNIT=Y) can have one of the above values.
			External partners (Z700-UNIT=N) must
			have the value "MED".
	3.5	TT/0	CONV: Default MED or relevant value.
Z700-ITEM-AVAIL-L- STATUS	M	X(3)	 DESC: Defines the status to assign to a lending request which fails to find a matching item for supply when the request is for a loan. Options: MED – Mediated. The request will go into the list of new incoming requests for ILL staff to review.
			AUF – Automatic Answer – Unfilled: the request goes into the list of unfilled incoming requests and a
			message is sent to the requesting library to say that the request is unfilled.
			This field is relevant only for internal partners.
			Internal partners (Z700-UNIT=Y) can have one of the above values.
			External partners (Z700-UNIT=N) must have the value "MED".
			nave the value "MED". CONV: Default MED or relevant value.

		1	
Z700-ITEM-AVAIL-C-	M	X(3)	DESC: Defines the status to assign to a
STATUS			lending request which fails to find a
			matching item for supply when the request is
			for a copy (physical copy or electronic
			copy). Options:
			MED – Mediated. The request will go into
			the list of new incoming requests
			for ILL staff to review.
			AUF – Automatic Answer – Unfilled: the
			request goes into the list of
			unfilled incoming requests and a
			message issent to the requesting
			library to say that the request is
			unfilled.
			This field is relevant only for internal
			partners.
			Internal partners (Z700-UNIT=Y) can have
			one of the above values.
			External partners (Z700-UNIT=N) must
			have the value "MED".
			CONV: Default MED or relevant value.