

Z112 – Valid Values for Fixed Length Forms

The Z112 is a BIB library table that contains a list of identifiers, values, and description to be used in the Fixed Length Fields Form of the Cataloging module.

Z112 records are created by loading configuration setup file/s (e.g. ./usm01/tab/tag_values.eng). The Z112 load is performed by running the batch service: "Import Database Tables - With Checks (file-06)".

Applying the Z112 identifiers in Cataloging Forms of Fixed-Length Fields displays the "List of Values" dialog box next to the relevant positions.

No conversion is needed for Z112.

For more information, refer to List of Values in Fixed-Length Fields Forms section of the Aleph 20.01 System Librarian Guide-Cataloging.

```

01  Z112-TAG-VALUES.
02  Z112-REC-KEY.
03  Z112-IDENTIFIER          PICTURE X(30).
03  Z112-LNG                 PICTURE X(3).
02  Z112-CODE                PICTURE X(10).
02  Z112-DESCRIPTION        PICTURE X(50).
  
```

Z112-IDENTIFIER	M	X(30)	DESC: The identifier code. When Z112 is loaded, the identifier code is taken from column 1 of the conf table (e.g. ./usm01/tab/tag_values.eng). For the same Z112-IDENTIFIER there might be several Z112 records depending on the numbers of lines set in the conf. table. After Z112 is loaded, Z112-IDENTIFIER can be set in the Cataloging 'Fixed-Length Form' file (e.g. ./usm01/pc_tab/catalog/008_bk.eng).
Z112-LNG	M	X(3)	DESC: The language code. When Z112 is loaded, the Z112-LNG code is taken from the conf table file name extension. E.g. when loading conf file: tag_values.eng, Z112-LNG is set to "ENG" Default value: ENG.
Z112-CODE	M	X(10)	DESC: The valid value for the identifier. When Z112 is loaded, Z112-CODE is taken from column 2 of the conf table.
Z112-DESCRIPTION	M	X(50)	DESC: The textual description of the

			Z112-CODE. When Z112 is loaded, Z112-DESCRIPTION is taken from column 3 of the conf table.
--	--	--	--

—