

Z700 – ILL Partner

The Z700 is a pw_library Oracle table that contains administrative information about ILL Partners.

An ILL partner is an administrative unit that sends ILL requests to you and/or that responds to your ILL requests for material. Each library or institution that is used as a player (requester or supplier) in the ILL flow, including your own administrative unit, has a partner record in the system.

There are three types of partners: internal partner, shared external partner, and non-shared external partner.

- **Internal Partner – also known as ILL Unit** – local administrative unit that handles ILL borrowing and lending activities. An ILL unit can be set up to represent a single sublibrary or a group of sublibraries.
- **Shared External Partner** – a supplier or a requester library which is not a part of any ADM library of your library system; it is external to your library system (for example, another library or a supplier like BLDSC). An external shared partner can be used as a supplier by all ADM libraries.
- **Non-shared External Partner** – a non-shared external partner is the same as a shared external partner, but it can be used as a supplier only by the library which created the partner record.

Each ILL partner (both external and internal) to whom you supply ILL material must have a parallel Patron record.

In the following Z700 table, (X) denotes an alphanumeric field and (9) denotes a numeric field. All alphanumeric fields are left-aligned with trailing spaces; all numeric fields are right-aligned with leading zeros. Decimal positions are indicated by the symbol V. The total number of decimal digits is designated by the number of nines following the V. Note that the decimal point is not stored in the field (for example, if the field definition is 9(4)V99, then 1000 = 10.00).

```
01  Z700.
    02  Z700-REC-KEY.
        03  Z700-INTERNAL-CODE          PICTURE X(20) .
    02  Z700-ILL-LIBRARY                PICTURE X(5) .
    02  Z700-UNIT                       PICTURE X(1) .
    02  Z700-PROTOCOL-TYPE              PICTURE X(5) .
    02  Z700-REC-KEY-2.
        03  Z700-PROTOCOL-CODE          PICTURE X(50) .
    02  Z700-E-INTERFACE.
        03  Z700-SERVER-ADDRESS          PICTURE X(100) .
    02  Z700-PRINT.
        03  Z700-PLAIN-HTML              PICTURE X(1) .
        03  Z700-LETTER-TYPE              PICTURE 9(2) .
        03  Z700-SEND-METHOD           PICTURE X(5) .
    02  Z700-NAME-KEY                   PICTURE X(40) .
    02  Z700-ISO-SUPPLIER-TYPE           PICTURE X(10) .
```

02	Z700-USER-ID	PICTURE X(50).
02	Z700-USER-PASSWORD	PICTURE X(50).
02	Z700-NAME	PICTURE X(150).
02	Z700-GENERAL-ADDRESS.	
03	Z700-GEN-ADDRESS-1	PICTURE X(100).
03	Z700-GEN-ADDRESS-2	PICTURE X(100).
03	Z700-GEN-ADDRESS-3	PICTURE X(100).
03	Z700-GEN-ADDRESS-4	PICTURE X(100).
03	Z700-GEN-ADDRESS-5	PICTURE X(100).
03	Z700-GEN-TELEPHONE	PICTURE X(20).
03	Z700-GEN-FAX	PICTURE X(20).
03	Z700-GEN-EMAIL-ADDRESS	PICTURE X(60).
03	Z700-GEN-STRUCTURED-ADDRESS.	
04	Z700-GEN-CITY	PICTURE X(50).
04	Z700-GEN-STATE	PICTURE X(50).
04	Z700-GEN-ZIP	PICTURE X(20).
04	Z700-GEN-COUNTRY	PICTURE X(50).
03	Z700-GEN-CONTACT.	
04	Z700-GEN-CONTACT-1	PICTURE X(200).
04	Z700-GEN-CONTACT-2	PICTURE X(200).
04	Z700-GEN-CONTACT-3	PICTURE X(200).
02	Z700-SHIPPING-ADDRESS.	
03	Z700-SHIP-ADDRESS-1	PICTURE X(100).
03	Z700-SHIP-ADDRESS-2	PICTURE X(100).
03	Z700-SHIP-ADDRESS-3	PICTURE X(100).
03	Z700-SHIP-ADDRESS-4	PICTURE X(100).
03	Z700-SHIP-ADDRESS-5	PICTURE X(100).
03	Z700-SHIP-TELEPHONE	PICTURE X(20).
03	Z700-SHIP-FAX	PICTURE X(20).
03	Z700-SHIP-EMAIL-ADDRESS	PICTURE X(60).
03	Z700-SHIP-STRUCTURED-ADDRESS.	
04	Z700-SHIP-CITY	PICTURE X(50).
04	Z700-SHIP-STATE	PICTURE X(50).
04	Z700-SHIP-ZIP	PICTURE X(20).
04	Z700-SHIP-COUNTRY	PICTURE X(50).
03	Z700-SHIP-CONTACT.	
04	Z700-SHIP-CONTACT-1	PICTURE X(200).
04	Z700-SHIP-CONTACT-2	PICTURE X(200).
04	Z700-SHIP-CONTACT-3	PICTURE X(200).
02	Z700-BILLING-ADDRESS.	
03	Z700-BILL-ADDRESS-1	PICTURE X(100).
03	Z700-BILL-ADDRESS-2	PICTURE X(100).
03	Z700-BILL-ADDRESS-3	PICTURE X(100).
03	Z700-BILL-ADDRESS-4	PICTURE X(100).
03	Z700-BILL-ADDRESS-5	PICTURE X(100).
03	Z700-BILL-TELEPHONE	PICTURE X(20).
03	Z700-BILL-FAX	PICTURE X(20).
03	Z700-BILL-EMAIL-ADDRESS	PICTURE X(60).
03	Z700-BILL-STRUCTURED-ADDRESS.	
04	Z700-BILL-CITY	PICTURE X(50).
04	Z700-BILL-STATE	PICTURE X(50).
04	Z700-BILL-ZIP	PICTURE X(20).
04	Z700-BILL-COUNTRY	PICTURE X(50).
03	Z700-BILL-CONTACT.	
04	Z700-BILL-CONTACT-1	PICTURE X(200).
04	Z700-BILL-CONTACT-2	PICTURE X(200).
04	Z700-BILL-CONTACT-3	PICTURE X(200).

```

02 Z700-NOTE PICTURE X(300).
  02 Z700-COPYRIGHT-STATEMENT PICTURE X(300).
  02 Z700-OPEN-DATE PICTURE 9(8).
  02 Z700-UPDATE-DATE PICTURE 9(8).
  02 Z700-STATUS PICTURE X(2).
  02 Z700-CON-LNG PICTURE X(3).
  02 Z700-CATALOGER PICTURE X(10).
  02 Z700-CURRENCY PICTURE X(3).
  02 Z700-AVG-SUPPLY-DAYS PICTURE 9(3).
  02Z700-DELIVERY-DELAY PICTURE 9(3).
  02 Z700-LOCATE-TYPE PICTURE X(10).
  02 Z700-CATALOG-TYPE PICTURE X(5).
  02 Z700-LOCATE-BASE PICTURE X(20).
  02 Z700-LOCATE-SERVER PICTURE X(100).
  02 Z700-LOCATE-CIRC-LIBRARY PICTURE X(5).
  02 Z700-ADDITIONAL-VENDOR-CODE PICTURE X(30).

02 Z700-BORROWING-ATTR.
  03 Z700-BORROWING-ALLOWED PICTURE X(1).
  03 Z700-AUTO-BORROWING-LOCATE PICTURE X(1).
  03 Z700-CHECK-LOCAL-OWN PICTURE X(1).
  03 Z700-SELF-OWN-L-STATUS PICTURE X(3).
  03 Z700-SELF-OWN-C-STATUS PICTURE X(3).
  03 Z700-REQUEST-PICKUP-LOCS.
    04 Z700-REQUEST-PICKUP-LOC OCCURS 100 PICTURE X(5).

02 Z700-LENDING-ATTR.
  03 Z700-LENDING-ALLOWED PICTURE X(1).
  03 Z700-AUTO-LENDING-LOCATE PICTURE X(1).
  03 Z700-CIRC-SUB-LIBRARIES.
    04 Z700-CIRC-SUB-LIBRARY OCCURS 100 PICTURE X(5).
  03 Z700-ITEM-LOC-L-STATUS PICTURE X(3).
  03 Z700-ITEM-LOC-C-STATUS PICTURE X(3).
  03 Z700-ITEM-AVAIL-L-STATUS PICTURE X(3).
  03 Z700-ITEM-AVAIL-C-STATUS PICTURE X(3).

02 Z700-E-INTERFACE-V6.
  03 Z700-SERVER-ADDRESS-V6 PICTURE X(100).

```

Z700-REC-KEY			
Z700-INTERNAL-CODE	M	X(20) Upper case	DESC: Unique key by which the system identifies the ILL partner. NOTE: For partners that are used as ILL requesters, set up to 12 alphanumeric characters. CONV: Relevant code.

Z700-ILL-LIBRARY	O/ M	X(5)	<p>DESC: The ILL library code (XXX40) to which the ILL partner belongs. Mandatory for ILL partner of type ILL Unit (Z700-UNIT=Y).</p> <p>Z700-ILL-LIBRARY field different between Shared External Partner and Non-Shared External Partner.</p> <p>Shared External Partner will have Z700-UNIT=N and null in Z700-ILL-LIBRARY. Non-Shared External Partner will have Z700-UNIT=N and ILL Library code Z700-ILL-LIBRARY.</p> <p>CONV: Blank or relevant value.</p>
Z700-UNIT	O	X(1)	<p>DESC: Y or N value. This value indicates the type of ILL partner, whether Internal (ILL Unit) or External (shared and non-shared).</p> <p>Y – The partner is an ILL Unit.</p> <p>N – The Partner is not an ILL Unit. It is an external partner (shared or non-shared).</p> <p>Blank – The same as "N". The Partner is not an ILL Unit. It is an external partner (shared or non-shared).</p> <p>CONV: Relevant value or blank.</p>
Z700-PROTOCOL-TYPE	M	X(5)	<p>DESC: The method in which your library sends communication to the partner.</p> <p>Options:</p> <p>ISO – ISO TCP protocol</p> <p>SLNP – German protocol</p> <p>DANZG – Danish Protocol</p> <p>LT – Letter: the partner uses letter-based communication, e.g.: email, fax, telephone</p> <p>BL – ARTel/ARTemail: the partner accepts the British Library protocol TX format</p> <p>CONV: Relevant code.</p>
Z700-PROTOCOL-CODE	M/ O	X(50)	<p>DESC: The partner institution symbol. E.g.: EXL:MN_LAW. Mandatory for Z700-PROTOCOL-TYPE =ISO. Not relevant for all other protocol types.</p> <p>CONV: Relevant value or blank.</p>
Z700-E-INTERFACE			<p>DESC: Details for dispatching ILL related communication in a non-letter format.</p> <p>Relevant only for Z700-PROTOCOL-TYPE =ISO.</p>

Z700-SERVER-ADDRESS	M/ O	X(100)	DESC: The server IP and port number to which ILL ISO APDU messages are sent to the partner. E.g: goldcoast:9002. Mandatory for Z700-PROTOCOL-TYPE =ISO. Not relevant for all other protocol types. CONV: Relevant value or blank.
Z700-PRINT			DESC: Details for dispatching ILL related communication in a letter format. Relevant only for Z700-PROTOCOL-TYPE =LT.
Z700-PLAIN-HTML	M/ O	X(1)	DESC: The mode in which Email is sent to the partner. Mandatory for Z700- SEND-METHOD= EMAIL. Not relevant for all other send methods types. Options: H – send e-mail as an attachment only P – send e-mail in the Email body only B – send e-mail in both modes: e-mail body and as an attachment CONV: Relevant value or blank.
Z700-LETTER-TYPE	M/ O	9(2)	DESC: Default letter type for letters that are sent to the partner. Mandatory if Z700-PROTOCOL-TYPE = LT. Recommended to also set for other protocol types. Values: 00-99. CONV: Relevant value. You may use "00" as a default.
Z700-SEND-METHOD	O/ M	X(5)	DESC: The method in which letters are sent to the partner. Mandatory if Z700-PROTOCOL-TYPE = LT. Recommended to also set for other protocol types. Options: PRINT EMAIL CONV: Relevant value or blank.
Z700-NAME-KEY	M	X(40) Lower case	DESC: Sort form of partner name. CONV: Leave blank. Created by the system when a table is loaded into ALEPH. Character conversion procedures for the creation of the field are defined in the tab_character_conversion_line table of the alephe/unicode directory (ILL_PARTNER_NAME_KEY instance).

Z700-ISO-SUPPLIER-TYPE	O	X(10)	DESC: Not currently in use. For future use: define the partner ISO mode for Z700-PROTOCOL-TYPE = ISO. Options are hard-coded and defined in ILL-ISO-TYPE menu of ./ill_library/tab/pc_tab_exp_field.<lng>: OCLC – OCLC RLG – RLIN CONV: Blank.
Z700-USER-ID	O	X(50)	DESC: Not currently in use. For futural usage: The library's user ID at the partner. CONV: Blank.
Z700-USER-PASSWORD	O	X(50)	DESC: Not in current use. For futural usage: The library's user PW at the partner vendor list. CONV: Blank.
Z700-NAME	M	X(150)	DESC: Name of the partner. It displays in the list of partners and is used for sorting the vendor list. CONV: Relevant text.
Z700-GENERAL-ADDRESS			DESC: General address details of the partner. If Z700-SHIPPING-ADDRESS and Z700-SHIP-STRUCTURED-ADDRESS or Z700-BILLING-ADDRESS and Z700-BILL-STRUCTURED-ADDRESS sections are left empty, the system will use Z700-GENERAL-ADDRESS and Z700-GEN-STRUCTURED-ADDRESS.
Z700-GEN-ADDRESS-1	O	X(100)	DESC: First line of the partner general address. Should be the same as Z700-NAME. CONV: Relevant text.
Z700-GEN-ADDRESS-2	O	X(100)	DESC: Second line of the partner general address. CONV: Relevant text.
Z700-GEN-ADDRESS-3	O	X(100)	DESC: Third line of the partner general address. CONV: Blank or relevant text.
Z700-GEN-ADDRESS-4	O	X(100)	DESC: Fourth line of the partner general address. CONV: Blank or relevant text.
Z700-GEN-ADDRESS-5	O	X(100)	DESC: Fifth line of the partner general address. CONV: Blank or relevant text.
Z700-GEN-TELEPHONE	O	X(20)	DESC: The partner general Tel. No. CONV: Blank or relevant text.
Z700-GEN-FAX	O	X(20)	DESC: The partner general Fax. No. CONV: Blank or relevant text.

Z700-GEN-EMAIL-ADDRESS	O	X(60)	DESC: The partner general Email address. CONV: Blank or relevant text.
Z700-GEN-STRUCTURED-ADDRESS.			DESC: Partner's general structured address.
Z700-GEN-CITY	O	X(50)	DESC: The partner general structured address: city. CONV: Blank or relevant text.
Z700-GEN-STATE	O	X(50)	DESC: The partner general structured address: state. CONV: Blank or relevant text.
Z700-GEN-ZIP	O	X(20)	DESC: The partner general structured address: zip code. CONV: Blank or relevant text.
Z700-GEN-COUNTRY	O	X(50)	DESC: The partner general structured address: country. CONV: Blank or relevant text.
Z700-GEN-CONTACT-1	O	X(200)	DESC: Name of the person to contact at the partner for general issues. CONV: Blank or relevant text.
Z700-GEN-CONTACT-2	O	X(200)	As Z700-GEN-CONTACT-1
Z700-GEN-CONTACT-3	O	X(200)	As Z700-GEN-CONTACT-1
Z700-SHIPPING-ADDRESS			DESC: Partner's address for shipping material. If Z700-SHIPPING-ADDRESS and Z700-SHIP-STRUCTURED-ADDRESS sections are empty, the system will use Z700-GENERAL-ADDRESS and Z700-GEN-STRUCTURED-ADDRESS.
Z700-SHIP-ADDRESS-1	O	X(100)	DESC: First line of the partner shipping address. CONV: Relevant text.
Z700- SHIP-ADDRESS-2	O	X(100)	DESC: Second line of the partner shipping address. CONV: Relevant text.
Z700- SHIP-ADDRESS-3	O	X(100)	DESC: Third line of the partner shipping address. CONV: Blank or relevant text.
Z700- SHIP-ADDRESS-4	O	X(100)	DESC: Fourth line of the partner shipping address. CONV: Blank or relevant text.
Z700- SHIP-ADDRESS-5	O	X(100)	DESC: Fifth line of the partner shipping address. CONV: Blank or relevant text.
Z700-SHIP-TELEPHONE	O	X(20)	DESC: The partner shipping Tel. No. CONV: Blank or relevant text.
Z700-SHIP-FAX	O	X(20)	DESC: The partner shipping Fax. No. CONV: Blank or relevant text.
Z700-SHIP-EMAIL-ADDRESS	O	X(60)	DESC: The partner shipping e-mail address. CONV: Blank or relevant text.

Z700-SHIP-STRUCTURED-ADDRESS.			DESC: Partner's shipping structured address.
Z700-SHIP-CITY	O	X(50)	DESC: The partner shipping structured address: city. CONV: Blank or relevant text.
Z700-SHIP-STATE	O	X(50)	DESC: The partner shipping structured address: state. CONV: Blank or relevant text.
Z700-SHIP-ZIP	O	X(20)	DESC: The partner shipping structured address: zip code. CONV: Blank or relevant text.
Z700-SHIP-COUNTRY	O	X(50)	DESC: The partner shipping structured address: country. CONV: Blank or relevant text.
Z700-SHIP-CONTACT-1	O	X(200)	DESC: Name of person to contact at the partner for shipping issues. CONV: Blank or relevant text.
Z700-SHIP-CONTACT-2	O	X(200)	As Z700-SHIP-CONTACT-1
Z700-SHIP-CONTACT-3	O	X(200)	As Z700-SHIP-CONTACT-1
Z700-BILLING-ADDRESS			DESC: Partner's address details for sending bills. If Z700-BILLING-ADDRESS and Z700-BILL-STRUCTURED-ADDRESS sections are empty, the system will use Z700-GENERAL-ADDRESS and Z700-GEN-STRUCTURED-ADDRESS.
Z700-BILL-ADDRESS-1	O	X(100)	DESC: First line of the partner billing address. CONV: Relevant text.
Z700-BILL-ADDRESS-2	O	X(100)	DESC: Second line of the partner billing address. CONV: Relevant text.
Z700- BILL-ADDRESS-3	O	X(100)	DESC: Third line of the partner billing address. CONV: Blank or relevant text.
Z700- BILL-ADDRESS-4	O	X(100)	DESC: Fourth line of the partner billing address. CONV: Blank or relevant text.
Z700-BILL-ADDRESS-5	O	X(100)	DESC: Fifth line of the partner billing address. CONV: Blank or relevant text.
Z700-BILL-TELEPHONE	O	X(20)	DESC: The partner billing Tel. No. CONV: Blank or relevant text.
Z700-BILL-FAX	O	X(20)	DESC: The partner billing Fax. No. CONV: Blank or relevant text.
Z700-BILL-EMAIL-ADDRESS	O	X(60)	DESC: The partner billing Email address. CONV: Blank or relevant text.
Z700-BILL-STRUCTURED-ADDRESS.			DESC: Partner's billing structured address.

Z700-BILL-CITY	O	X(50)	DESC: The partner billing structured address: city. CONV: Blank or relevant text.
Z700-BILL-STATE	O	X(50)	DESC: The partner billing structured address: state. CONV: Blank or relevant text.
Z700-BILL-ZIP	O	X(20)	DESC: The partner billing structured address: zip code. CONV: Blank or relevant text.
Z700-BILL-COUNTRY	O	X(50)	DESC: The partner billing structured address: country. CONV: Blank or relevant text.
Z700-BILL-CONTACT-1	O	X(200)	DESC: Name of person to contact at the partner for billing issues. CONV: Blank or relevant text.
Z700-BILL-CONTACT-2	O	X(200)	As Z700-BILL-CONTACT-1
Z700-BILL-CONTACT-3	O	X(200)	As Z700-BILL-CONTACT-1
Z700-NOTE	O	X(300)	DESC: Free text note. CONV: Blank or relevant text.
Z700-COPYRIGHT-STATEMENT	O	X(300)	DESC: Relevant for Australian libraries. The copyright statement text that is sent from the partner with each ISO ILL request that is dispatched to suppliers. Should be set for ILL Unit (Z700-UNIT=Y) of Australian libraries. Works in conjunction with ./alephe/tab100 flag: ILL-MODE=2 (Australian ILL Copyright mode).
Z700-OPEN-DATE	M	9(8) Format: YYYYMM DD	DESC: Date the partner record was opened. CONV: Relevant date or conversion date.
Z700-UPDATE-DATE	M	9(8) Format: YYYYMM DD	DESC: Date the partner record was modified. CONV: Relevant date or conversion date.
Z700-STATUS	O	X(2)	DESC: Status code of the partner. Optional alphanumeric code. Default values for the pull-down menu of the partner's information form in the ILL module are defined in the data_tab/pc_tab_exp_field.lng table of the library's tab directory under the ILL-PARTNER-STATUS section. CONV: Blank or relevant status.

Z700-CON-LNG	M	X(3)	DESC: Language of correspondences. This is the language of the forms that are sent to the partner. Possible values are defined in LANG menu of ./ill_library/tab/pc_tab_exp_field.<lng>. CONV: Valid language code.
Z700-CATALOGER	M	X(10)	DESC: User name of the librarian who last updated the partner record. CONV: Relevant user name or "CONV".
Z700-CURRENCY	O	X(3)	DESC: The partner local currency. CONV: Blank or Z83-CURRENCY-NAME.
Z700-AVG-SUPPLY-DAYS	M	9(3) Leading zeroes	DESC: Average Supply Days field. Number of days it takes for the partner to supply ILL material (average supply days). Z700- Z700-AVG-SUPPLY-DAYS is used as a default value for Z701-AVG-SUPPLY-DAYS. Z701-AVG-SUPPLY-DAYS is used to compute expected date of arrival of the material (Z411-EXPECTED-ARRIVAL-DATE). CONV: Relevant number of days or 000 if irrelevant.
Z700-DELIVERY-DELAY	M	9(3) Leading zeroes	DESC: Return Delay field. Number of days it takes for your library to return ILL material to the partner. Z700-DELIVERY-DELAY is used as a default value for Z701-DELIVERY-DELAY. This field is used to compute the due date given to the patron for an ILL item in the following way: When an ILL item is received from a supplier for a loan, the expected return date is specified by the supplier (Z411-EXPECTED-RETURN-DATE). The system calculates the due date given to the patron as follows: Z411-EXPECTED-RETURN-DATE minus Z701-DELIVERY-DELAY. If you leave Z700-DELIVERY-DELAY and Z701-DELIVERY-DELAY set as zeros, ALEPH will use a system-wide default value instead. This is set through the ill_return_for_user variable in the pc_server_defaults CONV: Relevant number of days or 000 if irrelevant.

Z700-LOCATE-TYPE	M	X(10)	<p>DESC: The mode in which ALEPH will attempt to locate material at the partner database. Options:</p> <p>UNIT- ILL Unit: Indicates that the partner is an internal partner. Set this value if Z700-UNIT=Y and the ILL unit has all data (BIB+Z30 Items) held in an ALEPH format.</p> <p>UNITLESS- ILL Unit with no item data in ALEPH format: Indicate that the partner is an internal partner. Set this value if Z700-UNIT=Y and the ILL unit has only BIB data in ALEPH format (without Z30-item data of ALEPH format).</p> <p>ALEPH – ALEPH ILS: Indicates that this is an external partner (not part of your ALEPH installation) with full ALEPH ILS (BIB+Z30 Items). This value can be set only if Z700-ILL-UNIT=N.</p> <p>ITEMLESS - ALEPH ILS with no item data in ALEPH format. Indicates that this is an external partner (not part of your ALEPH installation) with ALEPH ILS with no Item-Z30 data in ALEPH format. This value can be set only if Z700-ILL-UNIT=N.</p> <p>EXTERNAL – Z39.50 partner: Indicate that this is an external partner that you have set Z39.50 gate configuration to access its database. Set this value if Z700-UNIT=N and the partner's base is defined in your Z39.50 gate configuration.</p> <p>NONE – None of the above options are relevant for the partner OR there is no information about the partner database OR ALEPH is not expected to perform the 'locate' action at the partner's database. This value can be set only for Z700-UNIT=N.</p> <p>CONV: Relevant value.</p>
------------------	---	-------	--

Z700-CATALOG-TYPE	M/ O	X(5)	<p>DESC: The ALEPH catalog type of the partner.</p> <p>Mandatory for Z700-LOCATE-TYPE : UNIT, UNITLESS, ALEPH and ITEMLESS.</p> <p>Not relevant for Z700-LOCATE-TYPE NONE and EXTERNAL.</p> <p>The options are:</p> <p>UV - ALEPH Union View</p> <p>SBIB - ALEPH Single Bib database</p> <p>CONV: Blank for Z700-LOCATE-TYPE =NONE and EXTERNAL. Relevant value for all other locate types.</p>
Z700-LOCATE-BASE	M/ O	X(20)	<p>DESC: The partner base in which the 'BIB locate' is performed.</p> <p>Mandatory for Z700-LOCATE-TYPE: UNIT, UNITLESS, ALEPH, ITEMLESS and EXTERNAL.</p> <p>Not relevant for Z700-LOCATE-TYPE NONE. The base must be one of the bases defined in ./alephe_tab/tab_base.eng</p> <p>CONV: Blank for Z700-LOCATE-TYPE =NONE. Relevant value for all other locate types.</p>
Z700-LOCATE-SERVER	M/ O	X(100)	<p>DESC: The server name and port number of the partner's Web OPAC; for example: goldcoast:8991. Mandatory for Z700-LOCATE-TYPE: UNIT, UNITLESS, ALEPH, ITEMLESS. Not relevant for Z700-LOCATE-TYPE: EXTERNAL and NONE.</p> <p>CONV: Relevant value or blank.</p>
Z700-LOCATE-CIRC-LIBRARY	M/ O	X(5)	<p>DESC: The ADM library code of the partner. Mandatory for Z700-LOCATE-TYPE: UNIT and ALEPH. E.g.: USM50.</p> <p>Not relevant for Z700-LOCATE-TYPE: UNITLESS, ITEMLESS, EXTERNAL and NONE.</p> <p>CONV: Relevant value or blank.</p>
Z700-ADDITIONAL-VENDOR-CODE	O	X(30)	<p>DESC: The partner additional code or name</p> <p>CONV: Relevant text.</p>
Z700-BORROWING-ATTR.			<p>DESC: Internal partner's (ILL Unit) borrowing policy definitions.</p>

Z700-BORROWING-ALLOWED	M	X(1)	<p>DESC: Indicate whether the internal ILL partner is used as an ILL borrowing center and can serve patron's outgoing requests.</p> <p>Options: Y – ILL Borrowing activity is allowed. N – ILL Borrowing activity is blocked. Internal partners (Z700-UNIT=Y) can have Y or N. External partners (Z700-UNIT=N) must have the value "N".</p> <p>CONV: Relevant value.</p>
Z700-AUTO-BORROWING-LOCATE	M	X(1)	<p>DESC: Indicates whether all the internal partner's new borrowing requests are automatically handled by the ILL library automatic processing daemon (ue_19).</p> <p>Options: Y – Borrowing request will be handled by ue_19. N – Borrowing request will not be handled by ue_19. Internal partners (Z700-UNIT=Y) can have Y or N. External partners (Z700-UNIT=N) must have the value "N".</p> <p>CONV: Relevant value.</p>
Z700-CHECK-LOCAL-OWN	M	X(1)	<p>DESC: Indicates whether the internal partner will first check for self ownership when a new borrowing request is created.</p> <p>Options: 0 – No check 1 – Check for items existence. 2 – Allow ILL if patron is locally blocked. 3 – Block ILL if patron blocked/items available locally. Internal partners (Z700-UNIT=Y) can have one of the above values. External partners (Z700-UNIT=N) must have the value "0".</p> <p>CONV: Relevant value.</p>
Z700-SELF-OWN-L-STATUS	M	X(3)	<p>DESC: Defines the status a "returnable" borrowing request. It is given as a result of local ownership. The only option is LOW (Locally Owned).</p> <p>CONV: Always put: LOW.</p>

Z700-SELF-OWN-C-STATUS	M	X(3)	DESC: Defines the status a "non-returnable" borrowing request It is given as a result of local ownership. The only option is LOW (Locally Owned). CONV: Always put: LOW.
Z700-REQUEST-PICKUP-LOC	M/O	X(5) 100 occurrences	DESC: Defines up to 100 sublibraries from which the in ILL Unit's patrons are allowed to pick up. Mandatory only for Z700-UNIT=Y that its Z700-BORROWING-ALLOWED is set to 'Y'. The value entered in this field must be defined as a valid sublibrary in Col. 1 of ./alephe/tab/tab_sub_library.<lng>. Only sublibrary of type 1, 2, or 3 can be set in Z700-REQUEST-PICKUP-LOCs CONV: Blank or relevant value.
Z700-LENDING-ATTR.			DESC: Internal partner's (ILL Unit) lending policy definitions.
Z700-LENDING-ALLOWED	M	X(1)	DESC: Indicate whether the internal ILL partner is allowed ILL lending. Options: Y – ILL Lending activity is allowed. N – ILL Lending activity is blocked. Internal partners (Z700-UNIT=Y) can have Y or N. External partners (Z700-UNIT=N) must have the value "N". CONV: Relevant value.
Z700-AUTO-LENDING-LOCATE	M	X(1)	DESC: Indicate whether all the internal partner's new lending requests are automatically handled by the ILL library automatic processing daemon (ue_19). Options: Y – Lending request will be handled by ue_19. N – Lending request will not be handled by ue_19. Internal partners (Z700-UNIT=Y) can have Y or N. External partners (Z700-UNIT=N) must have the value "N". CONV: Relevant value.

Z700-CIRC-SUB-LIBRARY	M/ O	X(5) 100 occurrences	<p>DESC: Defines up to 100 sublibraries to which an item loaned by the ILL Unit must belong. An item can not be loaned by the ILL Unit if it does not belong to one of these sublibraries.</p> <p>Mandatory only for Z700-UNIT=Y that its Z700-LENDING-ALLOWED is set to 'Y'. The value entered in this field must be defined as a valid sublibrary in Col. 1 of <code>./alephe/tab/tab_sub_library.<lng></code>. Only sublibrary of type 1 can be set Z700-CIRC-SUB-LIBRARY. In case there are more than 100 sublibraries you may define a group code as defined in <code>./ill_library/tab/tab_sublib_group.<lng></code></p> <p>CONV: Blank or relevant value.</p>
Z700-ITEM-LOC-L-STATUS	M	X(3)	<p>DESC: Defines the status to assign to a lending request which fails to find a matching BIB record when the request is for a loan. Options:</p> <p>MED – Mediated. The request will go into the list of new incoming requests for ILL staff to review.</p> <p>AUF – Automatic Answer – Unfilled: the request goes into the list of unfilled incoming requests and a message is sent to the requesting library that the request is unfilled.</p> <p>This field is relevant only for internal partners.</p> <p>Internal partners (Z700-UNIT=Y) can have one of the above values.</p> <p>External partners (Z700-UNIT=N) must have the value "MED".</p> <p>CONV: Default MED or relevant value.</p>

Z700-ITEM-LOC-C-STATUS	M	X(3)	<p>DESC: Defines the status to assign to a lending request which fails to find a matching BIB record when the request is for a copy (physical copy or electronic copy). Options: MED – Mediated. The request will go into the list of new incoming requests for ILL staff to review. AUF – Automatic Answer – Unfilled: the request goes into the list of unfilled incoming requests and a message is sent to the requesting library to say that the request is unfilled.</p> <p>This field is relevant only for internal partners. Internal partners (Z700-UNIT=Y) can have one of the above values. External partners (Z700-UNIT=N) must have the value "MED". CONV: Default MED or relevant value.</p>
Z700-ITEM-AVAIL-L-STATUS	M	X(3)	<p>DESC: Defines the status to assign to a lending request which fails to find a matching item for supply when the request is for a loan. Options: MED – Mediated. The request will go into the list of new incoming requests for ILL staff to review. AUF – Automatic Answer – Unfilled: the request goes into the list of unfilled incoming requests and a message is sent to the requesting library to say that the request is unfilled.</p> <p>This field is relevant only for internal partners. Internal partners (Z700-UNIT=Y) can have one of the above values. External partners (Z700-UNIT=N) must have the value "MED". CONV: Default MED or relevant value.</p>

Z700-ITEM-AVAIL-C-STATUS	M	X(3)	<p>DESC: Defines the status to assign to a lending request which fails to find a matching item for supply when the request is for a copy (physical copy or electronic copy). Options:</p> <p>MED – Mediated. The request will go into the list of new incoming requests for ILL staff to review.</p> <p>AUF – Automatic Answer – Unfilled: the request goes into the list of unfilled incoming requests and a message is sent to the requesting library to say that the request is unfilled.</p> <p>This field is relevant only for internal partners. Internal partners (Z700-UNIT=Y) can have one of the above values. External partners (Z700-UNIT=N) must have the value "MED".</p> <p>CONV: Default MED or relevant value.</p>
Z700-SERVER-ADDRESS-V6	O	X(100)	<p>DESC: For future use.</p>