

Z14 – MEMBERS OF A ROUTING LIST

The Z14 table contains members of a routing list. It is complemented by Z18 (Routing list).

In the following table, (X) denotes an alphanumeric field and (9) denotes a numeric field. All alphanumeric fields are left-aligned with trailing spaces, all numeric fields are right-aligned with leading zeros. Decimal positions are indicated by the symbol V. The total number of decimal digits is designated by the number of nines following the V.

02	Z14-REC-KEY	
03	Z14-DOC-NUMBER	PICTURE 9(9).
03	Z14-COPY-SEQUENCE	PICTURE 9(5).
03	Z14-ROUT-SEQUENCE	PICTURE 9(2).
03	Z14-KEY-ID	PICTURE X(12).
02	Z14-USER-DATA.	
03	Z14-ALPHA	PICTURE X(1).
03	Z14-ID	PICTURE X(12).
03	Z14-PRIORITY	PICTURE 9(2).
03	Z14-GROUP	PICTURE 9(2).

Z14-REC-KEY			
Z14-DOC-NUMBER	M	9(9)	DESC: ADM system number. CONV: Administrative system number of the record associated to the members of the routing list.
Z14-COPY-SEQUENCE	M	9(5) leading zeroes	DESC: Sequence number of subscription within an ADM record. CONV: Sequential number, beginning with 00001 (relevant Z16-COPY-SEQUENCE).
Z14-ROUT-SEQUENCE	M	9(2)	DESC: Sequence number of a routing list, for a copy. Used to distinguish between multiple routing lists for the same subscription. CONV: Must be the same as the Z18-ROUT-SEQUENCE to which the member is linked.
Z14-KEY-ID	M	X(12)	DESC: User ID of the member. CONV: Patron's ID (Z303-ID).
Z14-USER-DATA			
Z14-ALPHA	M	X(1)	DESC: ALPHA code of the record. Use L for all scripts (e.g. Latin, Greek, Cyrillic, etc.). CONV: L.
Z14-ID	M	X(12)	DESC: User ID of the member. As in Z14-KEY-ID. CONV: Relevant ID.
Z14-PRIORITY	M	9(2)	DESC: Priority of each member in the routing list. CONV: Put zeroes as default or relevant priority.
Z14-GROUP	M	9(2)	DESC: This variable can be used by an external program to create another level of priority. The Z14-GROUP has no effect on-line. CONV: Put 50 as default.