

## Z14 – MEMBERS OF A ROUTING LIST

The Z14 table contains members of a routing list. It is complemented by Z18 (Routing list).

In the following table, (X) denotes an alphanumeric field and (9) denotes a numeric field. All alphanumeric fields are left-aligned with trailing spaces, all numeric fields are right-aligned with leading zeros. Decimal positions are indicated by the symbol V. The total number of decimal digits is designated by the number of nines following the V.

|    |                   |                |
|----|-------------------|----------------|
| 02 | Z14-REC-KEY       |                |
| 03 | Z14-DOC-NUMBER    | PICTURE 9(9).  |
| 03 | Z14-COPY-SEQUENCE | PICTURE 9(5).  |
| 03 | Z14-ROUT-SEQUENCE | PICTURE 9(2).  |
| 03 | Z14-KEY-ID        | PICTURE X(12). |
| 02 | Z14-USER-DATA.    |                |
| 03 | Z14-ALPHA         | PICTURE X(1).  |
| 03 | Z14-ID            | PICTURE X(12). |
| 03 | Z14-PRIORITY      | PICTURE 9(2).  |
| 03 | Z14-GROUP         | PICTURE 9(2).  |

|                      |   |                        |  |
|----------------------|---|------------------------|--|
| <b>Z14-REC-KEY</b>   |   |                        |  |
| Z14-DOC-NUMBER       | M | 9(9)                   | <b>DESC:</b> ADM system number.<br><b>CONV:</b> Administrative system number of the record associated to the members of the routing list.  |
| Z14-COPY-SEQUENCE    | M | 9(5)<br>leading zeroes | <b>DESC:</b> Sequence number of subscription within an ADM record.<br><b>CONV:</b> Sequential number, beginning with 00001 (relevant Z16-COPY-SEQUENCE).   |
| Z14-ROUT-SEQUENCE    | M | 9(2)                   | <b>DESC:</b> Sequence number of a routing list, for a copy. Used to distinguish between multiple routing lists for the same subscription.<br><b>CONV:</b> Must be the same as the Z18-ROUT-SEQUENCE to which the member is linked. |
| Z14-KEY-ID           | M | X(12)                  | <b>DESC:</b> User ID of the member.<br><b>CONV:</b> Patron's ID (Z303-ID).   |
| <b>Z14-USER-DATA</b> |   |                        |  |
| Z14-ALPHA            | M | X(1)                   | <b>DESC:</b> ALPHA code of the record. Use <b>L</b> for all scripts (e.g. Latin, Greek, Cyrillic, etc.).<br><b>CONV:</b> L.  |
| Z14-ID               | M | X(12)                  | <b>DESC:</b> User ID of the member. As in Z14-KEY-ID.<br><b>CONV:</b> Relevant ID.   |
| Z14-PRIORITY         | M | 9(2)                   | <b>DESC:</b> Priority of each member in the routing list.<br><b>CONV:</b> Put zeroes as default or relevant priority.  |
| Z14-GROUP            | M | 9(2)                   | <b>DESC:</b> This variable can be used by an external program to create another level of priority. The Z14-GROUP has no effect on-line.<br><b>CONV:</b> Put 50 as default.   |